




The University of Notre Dame Australia uses an encrypted wireless network, to ensure that all information is protected.

To access the wireless network, you must have an active staff or student username and password. Access to the university Wi-Fi is granted under the same policies as accessing our wired network.

The following connection to the UNDA-WiFi was tested on a Chromebook with latest updates installed. Some of the terminology and captured screenshot may be different from current version of Chromebook OS.

1. Click the **network icon** in the lower-right corner of your screen. 
2. Select WiFi Network **UNDA-WiFi**

3. Enter the following details to join the network
 - **SSID:** UNDA-WiFi
 - **EAP Method:** PEAP
 - **Phase 2 authentication:** MSCHAPv2
 - **Server CA Certificate:** Default
 - **User Certificate:** None Installed
 - **Identity:** Student/ Staff ID
 - **Password:** Student/ Staff password
 - **Anonymous Identity:** Empty

A screenshot of the 'Join Wi-Fi network' dialog box in Chrome OS. The dialog has a title bar with a close button (X) in the top right corner. The main content area is titled 'Join Wi-Fi network' and contains several input fields and dropdown menus. The fields are: SSID (text input with 'UNDA-WiFi'), EAP method (dropdown menu with 'PEAP'), Phase 2 authentication (dropdown menu with 'MSCHAPv2'), Server CA certificate (dropdown menu with 'Do not check'), User certificate (dropdown menu with 'None installed'), Identity (text input with '31001234'), Password (password input with '*****' and an eye icon to toggle visibility), and Anonymous identity (empty text input). At the bottom, there is a checkbox labeled 'Save identity and password' which is checked.

Join Wi-Fi network

SSID: UNDA-WiFi

EAP method: PEAP

Phase 2 authentication: MSCHAPv2

Server CA certificate: Do not check

User certificate: None installed

Identity: 31001234

Password: *****

Anonymous identity:

Save identity and password

4. Click **Connect**

Please kindly contact your campus Service Desk if you require assistance.

Fremantle

08 9433 0777
8am – 5pm WAST

fremantle.it@nd.edu.au

Sydney

02 8204 4444
8am – 5pm AEST

sydney.it@nd.edu.au

Broome

08 9192 0632
8am – 4:30pm WAST

broome.it@nd.edu.au